

fcluster-help


1.0

Generated by Doxygen 1.9.1

- 1 FLCLUSTER Users Manual - Version 1.1** **1**
- 1.1 Logging on to remote host 2
- 1.1.1 Managing Hosts 3
- 1.1.2 Initial Host Commands 4
- 1.1.3 Command Macros 5
- 1.1.4 Spot when logged 7
- 1.1.5 Auto Connect to Host 7
- 1.2 DX cluster color scheme 7
- 1.3 TelNet stream 8
- 1.3.1 Submitting a spot 8
- 1.3.2 DX cluster reports 9
- 1.4 I/O Interface 10
- 1.4.1 Fldigi Interface 10
- 1.4.2 DX Cluster QSY logic 10
- 1.4.3 Server Help URLs 11
- 1.5 On Line Cluster Help 11

Chapter 1

FLCLUSTER Users Manual - Version 1.1



flcluster connects to and displays data from DX cluster servers. The three most common server types are AR-Cluster, CC-Cluster, and DX Spider. The program is designed to work stand alone or as a helper application to fldigi. It can transfer call, mode, and frequency data from a spotted QSO to the appropriate fldigi controls. It can query fldigi for the same items when generating a spot report.


1.1 Logging on to remote host

Before any logon you should configure fcluster with your basic personal information. Check the "Enable Tooltips" if you want a small tooltip popup window to display when the cursor hovers over an fcluster control.

fcluster needs to occasionally send a backspace character (keepalive) to the cluster server. The server echos the backspace. If the echo is not received within a 30 second window then the server connection is assumed to be down. fcluster will attempt to reconnect if this occurs. Receipt of a broadcast message such as a dx spot report within the keepalive time interval will reset the timer. You can set the keepalive interval to 1, 5, or 10 minutes. 5 should probably suffice for most servers and internet paths.


Enter the DX HOST hostname/IP, the Port and your Login call. Then check the "Connect" control. The "Connected" label will be visible only after the remote host connection has been made.

Immediately after checking the "Connect" control the dxcluster dialog should change to the "TelNet stream" tab. This tab displays the raw telnet data stream, shown here for the GB7DJK server, GB7DKJ.dxcluster.net.



1.1.1 Managing Hosts

You can maintain a list of remote hosts to which you can reliably connect and which provide good information relative to your QRA (Maidenhead locator). The following refers to the Cluster Config tab.



- Add the current host to the list using the "Add" button.
- Highlight an entry and press the "Select" button to transfer the elements to the connect controls.
- Highlight an entry and press the "Delete" button to delete an entry.

Press the "Servers" button if you are unfamiliar with the telnet address and port number of a convenient dxcluster server. flcluster will open up a local html document with a list of recently verified servers:

DXCluster - Telnet Directory					
From DX Cluster Info (2017-10-09)					
4X - Israel	9A - Croatia	9H - Malta	9K - Kuwait	9M2 - West Malaysia	BY - China
CE - Chile	CT - Portugal	CT3 - Madeira Islands	CX - Uruguay	DL - Germany	E7 - Bosnia & Herzegovina
EA - Spain	EA6 - Balearic Islands	EL - Ireland	EU - Belarus	F - France	G - England
GU - Guernsey	HA - Hungary	HB - Switzerland	HI - Dominican Republic	HL - South Korea	HP - Panama
HS - Thailand	I - Italy	IS0 - Sardinia	IT - Sicily	JA - Japan	K - United States
KH6 - Hawaii	KL7 - Alaska	KP4 - Puerto Rico	LA - Norway	LU - Argentina	LX - Luxembourg
LZ - Bulgaria	OE - Austria	OH - Finland	OK - Czech Republic	ON - Belgium	OZ - Denmark
SV5 - Dodecanese	TA - Turkey	TF - Iceland	TR - Gabon	UA - European Russia	UA9 - Asiatic Russia
UN - Kazakhstan	P4 - Aruba	PA - Netherlands	PY - Brazil	S5 - Slovenia	SM - Sweden
SP - Poland	SV - Greece	UT - Ukraine	VE - Canada	VK - Australia	YB - Indonesia
YL - Latvia	YO - Romania	YU - Serbia	YV - Venezuela	ZL - New Zealand	ZS - South Africa

NODECALL & IP	LOCATION/GRID	WEB/RF PORT	SYSOP/EMAIL	NOTES/SOFTWARE
4X - Israel				
4Z5LZ-2 cqplanet.com:7300	Modiin KM71lv		Alex 4Z5LZ	Home Page DX Spider ver. 1.55
9A - Croatia				
9A0CSJ dxc.ham.hr:7300	Sibenik JN73wr		Damir 9A4NF	DX Spider ver. 1.51
9A0DXC 9a0dxc.hamradio.hr:8000	Zagreb JN75xt		Tihomir 9A4GL	Node information DX Spider ver. 1.55
9A0DXV 9a0dxv.hamradio.hr:8000	Varazdinske Toplice JN86ff		Damir 9A30W	DX Spider ver. 1.55
9A1CIG-2 (+CW Skimmer) dxc9a1cig.no-ip.org	Kastel Gomilica, Croatia JN83en	Web	Zeljko 9A7JIV	Radio Club Kastilac AR-Cluster ver. 6.1.5123

You can configure flcluster to open a www page for the "Srvrs", "AR ?", "CC ?", and "DX ?" buttons. See [Server Help URLs](#).

With the exception of the cluster server setup commands (next section), flcluster will automatically save changes that you make in it's configuration. flcluster saves all setup and other related files to it's working folder:

Operating System	Folder/Directory
Windows	C:\Documents and Settings\ <username>\flcluster.files</username>
Vista	C:\Users\ <username>\flcluster.files</username>
Linux	/home/<username>/flcluster
Apple OS X	/Users/User_Login_Name/flcluster

1.1.2 Initial Host Commands



Most cluster servers will save your setup commands from a previous telnet session. You can also store those commands in the text editing control, "Cluster Server Setup Cmds."

You can save and reload any number of command sequences. Each is saved in a plain text file in the flcluster files subfolder "Scripts". The default extension for the dxcluster scripts is "dxc". Be sure you add the extension to your saved files. It will not be added if you do not with the result that file may not be visible when you try to load it.

Send the script to the remote server using the "Send" button. The transmission and response will be available for viewing on the "TelNet stream" tab.

1.1.3 Command Macros

Configure each of the 32 command macro buttons. The m1...m32 controls are the button label and the corresponding multi-line text control are the associated server commands. The macro editor is arranged in two banks of 16



Label	Macro Text	Label	Macro Text
M17	VK9XG !SH/DX 25 VK9X	M25	!SH/DX 25
M18	ZL7A !SH/DX 25 ZL7A	M26	!SH/DX 25
M19	!SH/DX 25	M27	!SH/DX 25
M20	!SH/DX 25	M28	!SH/DX 25
M21	!SH/DX 25	M29	!SH/DX 25
M22	!SH/DX 25	M30	!SH/DX 25
M23	!SH/DX 25	M31	!SH/DX 25
M24	!SH/DX 25	M32	!SH/DX 25

DX cluster command help can be viewed for each of the 3 server types.
Press the corresponding help button:

Home Bookmarks Most Visited Linux Mint My Groups W1HKJ Software fldigi NOAA QRZ Modem >>

AR Commands

Overview of AR-Cluster User Commands

The following list is a summary of AR-Cluster commands. The upper case part of the commands is required and the lower case part of the command is optional. Thus the command **A/F** is the same as the **Announce/Full** command.

Announce	Announcement to all locally users
Announce/Full	Announcement to all users
Bye	Terminate the connection to the cluster
CLEAR/QL	Remove a QSL route from the local QSL database
CONFERENCE	Enter a local conference
CONFERENCE/Full	Enter a network wide conference

Home Bookmarks Most Visited Linux Mint My Groups W1HKJ Software fldigi NOAA QRZ Modem >>

CCC Commands

CC Cluster Commands

ANnounce	Send an announcement to local USERS. (AN<Text Message>)
ANnounce/Full	Send an announcement to all nodes and USERS. (AN/F <Text Message>)
BYE	Disconnect from the node. (BYE) or (B)
DX	Send a DX spot. (DX <Callsign> <Frequency> or DX <Frequency> <Callsign>)
DXTest	Returns to USER only. (DXT P5NOW 14006.06) Good for testing RES 1 & RES 2



The macro commands are available on the *TelNet Stream* tab in two banks of 16. Access to bank 1 or bank 2 is obtained using the up/down arrow button to the right of the macro buttons.

1.1.4 Spot when logged

Enable the "Spot when logged" in fldigi if you want to create the spot report whenever you log a contact from the fldigi main dialog. You will still have to review the spot report and submit it with the Submit button. You must be connected to fldigi for this to work.

1.1.5 Auto Connect to Host

Enable the "Auto Connect" if you want to connect to the host when starting fldigi.

1.2 DX cluster color scheme

You can change the text colors, and text fonts on the User config tab.



1.3 TelNet stream

The raw data to and from the cluster server is shown on the TelNet stream tab. Sent data is in red and received data is in black.

```

Date      Hour  SFI  A  K Exp.K  R SA  GMF  Aurora  Logger
15-Nov-2023  08  124  7  2   0 86 eru  act    no  <DK0WCY>
=====
Nodes: 23/389 Users [Loc/Clr]: 47/3663 Max: 102/6277 - Uptime: 14d 6h 41m
W1HKJ de GB7DJK 15-Nov-2023 0844Z dxspider >
*** Connected to GB7DJK, Graffham, West Sussex
DX de DL1NCH: 14303.0 SP9PF 73' Jacek in Kevelaer J031cn 0844Z
DX de F4CX0: 50067.8 LZ1WF/B JN26PP<ES>KN22HI 529 0844Z
DX de KC8YJJ: 10137.3 F1HFP 0844Z OH
W1HKJ de GB7DJK 15-Nov-2023 0845Z dxspider >
DX de UA3GT: 14135.0 UA3GT CQ CQ 0845Z
DX de IT9VDQ: 14140.4 R3MD TNX YR-03 USB 0845Z
DX de EA2CPG: 7120.0 EA3DUR DIPLOMA DIA DEL NI 0 0845Z
DX de VK4SMA: 7144.0 VK2IO WWFF VKFF-0292 0846Z
DX de VK2JJM: 14075.5 F5SG 0846Z
DX de DL6BF: 70021.0 OZ7IGY/B J032QI<TR>J055 PI4max -14db,no 0846Z

```

The TelNet stream text display is context sensitive to the right mouse button. You can copy marked text or delete the display contents using the right mouse button.

You can send individual commands to the remote host using the "Cmd:" control. Enter the command, for example: "SHow/FILTER", or "SH/FILTER". Then press the "Submit" button. The command string will be sent to the remote server and you can view the results on the "TelNet stream" tab.

During a logon to the remote host fclcluster will send some default commands depending on the host type. If the remote host is either an CC-Cluster or DX Spider host then fclcluster will send this sequence:

```

set/page 0
set/name [user name]
set/qth [user qth]
set/qra [user locator]

```

Where the [] values are those entered on the main "User" configuration tab.

Sending prepared (macro) commands or dx spot reports to the remote server is a two step process. Pressing any of the 32 macro buttons will transfer the macro string to the Cmd: control. You can modify the command string before pressing the Submit button.

1.3.1 Submitting a spot

You generate a spot report using the Spot button on the TelNet stream tab. Fclcluster will generate a spot report that tries to provide the cluster with some mode details. For example:


```

dx 3512.4 K2LBM RTTY [85] mode is RTTY, Mark frequency @ 3512.485
dx 3581.1 K2LBM MFSK16 [50] mode is MFSK16, center frequency @ 3581.150
dx 3580.8 K2LBM OLIVIA [00] mode is OLIVIA (8-500), center frequency @ 3580.800

```

Unfortunately, the ADIF mode specifier does not provide details regarding mode characteristics. The [0..99] values in the notes field denote the additional Hertz and tens-of-Hertz needed to specify the frequency to the nearest Hertz rather than rounded as is usually reported in the cluster spot report. This field is only added to the report if the "Report [0..99 Hz]" control is enabled on the dxcluster configure tab.

You enable the [hz] report in the comments section by checking this configuration control:



Pressing either of the SPOT buttons only adds the spot report to the Cmd: control. You can then modify the spot report before actually submitting the report using the Submit button.

1.3.2 DX cluster reports

fldigi parses the received data stream and displays each dx spot in a tabular form on the "DX Reports" tab:

The screenshot shows the 'DX Reports' window in fldigi. At the top, there are fields for 'DX HOST hostname/IP' (GB7DJK.DXCLUSTER.NET), 'Port' (7300), 'Login as' (W1HKJ), and 'Password' (with a question mark). There are also checkboxes for 'Connect' (checked) and 'Auto conn' (unchecked). Below these are tabs for 'TelNet stream', 'DX Reports', 'Cluster Config', 'Macros', 'I/O config', 'User Config', and 'Cluster Help'. The main area contains a table with columns: Spotter, Freq, Dx Call, Comments, UTC, and QRA. The table lists several spot reports, including DL1NCH, F4CX0, UA3GT, IT9VDQ, EA2CPG, VK4SMA, DL6BF, IZ80LR, BI8FRF, and IW0GNC. At the bottom, there are controls for 'New entries in first line', 'Align Cols', 'Clear', a time display '08:47:34 Z', and a 'Spot' button.

Spotter	Freq	Dx Call	Comments	UTC	QRA
DL1NCH	14303.0	SP9PF	73' Jacek in Kevelaer J031cn	0844Z	
F4CX0	50067.8	LZ1WF/B	JN26PP<ES>KN22HI 529	0844Z	
UA3GT	14135.0	UA3GT	CQ	Ci 0845Z	
IT9VDQ	14140.4	R3MD	TNX YR-03 USB	0845Z	
EA2CPG	7120.0	EA3DUR	DIPLOMA DIA DEL NIÑO	0845Z	
VK4SMA	7144.0	VK2IO	WWFF VKFF-0292	0846Z	
DL6BF	70021.0	OZ7IGY/B	J032QI<TR>J055 PI4max -14db,no	0846Z	
IZ80LR	7087.0	IZ8FCA	AWARD IONOTEST	0847Z	
BI8FRF	24971.0	SV9ANK	tnx73	0847Z	
IW0GNC	7117.0	IZ0PAP	award vulcani attivi sicilia	0847Z	

If connected to fldigi, left clicking on a spotted report line will transfer the frequency and mode to fldigi's operating parameters. The mode change is contingent on the mode being reported by the spotter and included in the 'Notes' block.

You can elect to view the reports with the most recent on either the top or the bottom of the list.

1.4 I/O Interface

1.4.1 Fldigi Interface

Use the default address and port entries for fldigi, unless you have specifically changed those for the currently running fldigi. fclcluster and fldigi do not have to be executing on the same computer. Enter the address as a LAN or WAN URL or socket address as appropriate.

- Socket address: 127.0.0.1
- Socket port : 7362

If fldigi is currently executing, then fclcluster will connect as soon as the "connect to Fldigi" box is checked. fclcluster will automatically connect to fldigi if you exit fclcluster with that box checked.

1.4.2 DX Cluster QSY logic

Set the PSK, CW and RTTY sweet spots to be identical to those in fldigi.

The xcvr set up and RTTY Mark Freq check boxes should be self explanatory. The state of these controls will determine how fclcluster calculates the transceiver suppressed carrier / audio (waterfall) track points. The computed values will be sent to fldigi when a spotted QSO is activated on the DX Reports tab.

A cluster spot report line has this format:

```
--SPOTTER---<-FREQ--><-DX STA---><-----NOTES-----><-UTC><LOC-->
KB80      14240.0  D66D           up 10 59 Ohio           2059Z EN81
```

fldigi will change mode if and only if the NOTES block contains a valid ADIF mode specifier, i.e. CW, PSK31, QPSK63, RTTY, etc.

The QSY logic does not make any assumptions regarding band, sub band in determining the RF carrier and AF injection frequency.

If the fldigi mode is SSB (available on the mode menu), then the QSY is to the FREQ value with no change in the WF tracking frequency.

Otherwise the existing mode or the mode detected in the NOTES is used to determine the QSY values:

```
CW:   QSY is based on the CW sweet spot
RTTY: QSY is based on the RTTY sweet spot
PSK:  QSY is based on the PSK sweet spot
DIGI: QSY is based on the PSK sweet spot
```

Most DX reports do not include a mode usage. Ergo it is up to the user to know what mode he or she is interested in. Are you spotting SSB, then change the fldigi mode to SSB. Are you interested in CW? Then change the mode to CW. This is really a KISS approach that is constrained by the very limited amount of data contained in the DX spot report.

1.4.3 Server Help URLs

fldcluster can generate a set of html pages for

- Cluster servers - Srvrs
- AR cluster help - AR
- CC cluster help - CC
- DX cluster help - DX

The internal html pages will be viewed when INTERNAL is specified as the respective URL. You can enter a web page for any of the four pages. Use the standard entry that would be in the URL bar of a web browser.

1.5 On Line Cluster Help

The Help tab provides a convenient access to help obtained directly from the dxcluster server. It is the equivalent of using the HELP command from the Cmd: control. The difference is that the server reply is parsed and presented in a separate text viewer.

